

USB Updating Instructions


In order to make this process simpler, we created two USB updates. The first one is a large download that helps you update any version of the ZoomText USB to the latest version. The second update is a smaller download, and will help you update from 9.18.x version to the latest version. It is advisable that you make a backup of your USB before attempting to do any changes to it.

1. Insert ZT USB device into a USB slot on the computer.
2. When the "Auto Play Window" comes up, cancel it by clicking on the X at the top right corner.




3. For the ZT USB versions 9.18.x, then you can just download and run the smaller update found here: <http://liveupdate.zoomtext.com/9.18.LatestUSBFor9.18.x.exe>
4. If you do not know what version of the USB that you have. Or if the USB version is 9.14 and earlier versions, then download and run the larger update: <http://liveupdate.zoomtext.com/9.18.LatestUSBFor9.1x.exe>

Click the "Finish" button on the "ZoomText USB Installation Directory" dialog box.



5. When the ZoomText USB Update dialog box opens, it is assumed that you have made a backup of the USB from before, so just answer "No" to that question. Otherwise click "Yes" to backup the ZT USB.



6. Click "OK" to the "Insert USB" message box.



After the update process is done, a message box will open indicating that your USB was successfully updated. So now your ZoomText USB version will be the latest version.



You can verify the ZoomText USB version by right clicking on the file USB_Drive_letter:\Setup\Support\ZxpInstDrv.dll, then left clicking **Properties**. Click on the **Details** tab to see the "File Version" as below:

